



# NiCE

## NDMP バックアップのフェーズ II の開始時にソケットが閉じる

[https://kb-japan.netapp.com/on-prem/ontap/dp/NDMP/NDMP-KBs/Socket\\_closes\\_in\\_the\\_beginning\\_of\\_Ph...](https://kb-japan.netapp.com/on-prem/ontap/dp/NDMP/NDMP-KBs/Socket_closes_in_the_beginning_of_Ph...)

Updated: Mon, 21 Sep 2026 21:43:39 GMT

### 環境

- ONTAP 9
- NDMP
- DMA (Data Management Application - Backup Application)

### 問題

- DMA接続テープ ライブラリを使用している場合、**Phase II** の開始時にNDMPバックアップが失敗する

ログに表示されるエラー メッセージ：

```
dmp Sun Mar 20 21:33:48 AEDT 202 /G8PPSS1009-SVM-A2R/PVOL_Westpac_WS(1)
Phase_change (II)
dmp Sun Mar 20 21:33:48 AEDT 202 /G8PPSS1009-SVM-A2R/PVOL_Westpac_WS(1)
Log_msg (Write DIRNET for BKP ID=3929, type=3 failed because bkp_out is
closing)
dmp Sun Mar 20 21:33:48 AEDT 202 /G8PPSS1009-SVM-A2R/PVOL_Westpac_WS(1)
Error (Write to socket failed)
dmp Sun Mar 20 21:33:48 AEDT 202 /G8PPSS1009-SVM-A2R/PVOL_Westpac_WS(1)
Tape_close (ndmp)
dmp Sun Mar 20 21:33:48 AEDT 202 /G8PPSS1009-SVM-A2R/PVOL_Westpac_WS(1)
Log_msg (Flush DIRNET called on error = 4.)
```